



MyID
Version 11.6

Self-Service Kiosk
Installation and Configuration Guide

Lutterworth Hall, St Mary's Road, Lutterworth, Leicestershire, LE17 4PS, UK
www.intercede.com | info@intercede.com | [@intercedemyid](https://twitter.com/intercedemyid) | +44 (0)1455 558111

Copyright

© 2001-2020 Intercede Limited. All rights reserved.

Information in this document is subject to change without notice. The software described in this document is furnished exclusively under a restricted license or non-disclosure agreement. Copies of software supplied by Intercede Limited may not be used resold or disclosed to third parties or used for any commercial purpose without written authorization from Intercede Limited and will perpetually remain the property of Intercede Limited. They may not be transferred to any computer without both a service contract for the use of the software on that computer being in existence and written authorization from Intercede Limited.

The software or web site referred to in this manual may utilize or contain material that is © 1994-2000 DUNDAS SOFTWARE LTD., all rights reserved.

No part of this publication may be reproduced, stored in a retrieval system or transmitted in any form or any means electronic or mechanical, including photocopying and recording for any purpose other than the purchaser's personal use without the written permission of Intercede Limited.

Whilst Intercede Limited has made every effort in the preparation of this manual to ensure the accuracy of the information, the information contained in this manual is delivered without warranty, either express or implied. Intercede Limited will not be held liable for any damages caused, or alleged to be caused, either directly or indirectly by this manual.

Licenses and Trademarks

The Intercede® and MyID® word marks and the MyID® logo are registered trademarks of Intercede in the UK, US and other countries.

Microsoft and Windows are registered trademarks of Microsoft Corporation. Other brands and their products are trademarks or registered trademarks of their respective holders and should be noted as such. All other trademarks acknowledged.

Conventions Used in this Document

- Lists:
 - ♦ Numbered lists are used to show the steps involved in completing a task when the order is important
 - ♦ Bulleted lists are used when the order is unimportant or to show alternatives

- **Bold** is used for menu items and for labels.
For example:
 - ♦ “Record a valid email address in **‘From’ email address**”
 - ♦ Select **Save** from the **File** menu

- *Italic* is used for emphasis and to indicate references to other sections within the current document:
For example:
 - ♦ “Copy the file *before* starting the installation”
 - ♦ “See *Issuing a Card* for further information”

- ***Bold and italic*** are used to identify the titles of other documents.
For example: “See the ***Release Notes*** for further information.”
Unless otherwise explicitly stated, all referenced documentation is available on the installation media.

- A `fixed width` font is used where the identification of spaces is important, including filenames, example SQL queries and any entries made directly into configuration files or the database.

- **Notes** are used to provide further information, including any prerequisites or configuration additional to the standard specifications.
For example:
Note: This issue only occurs if updating from a previous version.

- Warnings are used to indicate where failure to follow a particular instruction may result in either loss of data or the need to manually configure elements of the system.
For example:

Warning: You must take a backup of your database before making any changes to it.

Contents

Self-Service Kiosk	1
1 Introduction	5
1.1 Change history	5
2 Installing the Self-Service Kiosk	6
2.1 Prerequisites	6
2.1.1 Communication between the Self-Service Kiosk and MyID	6
2.1.2 Minimum client PC specifications	6
2.1.3 Supported operating systems	6
2.1.4 Supported biometrics	7
2.2 Running the installation program	7
2.2.1 Installing the Self-Service Kiosk silently	8
3 Overview	9
3.1 Architecture	9
3.2 Self-Service Kiosk	10
3.3 Authentication	11
3.4 Self-Service Kiosk features	12
4 Configuring the Self-Service Kiosk	13
4.1 Setting errors to silent	13
4.2 Server location	13
4.3 Kiosk page timeout	14
4.4 Setting up SSL	14
4.4.1 One-way SSL	14
4.4.2 Two-way SSL	14
4.5 Accessing the web services for the first time	15
4.6 Running the Self-Service Kiosk	16
4.6.1 Command-line parameters	16
4.6.2 Closing down the Kiosk	16
4.7 Translating the user interface	16
4.8 Logging	16
4.9 Job filtering	16
4.10 Temporary credential profile	17
4.11 Signature validation	17
5 Troubleshooting	19
6 Known Issues	20

1 Introduction

This document describes the installation and configuration of the MyID® Self-Service Kiosk.

The Self-Service Kiosk is designed to run on a shared PC and allow any cardholder to collect, activate or update their devices, and to request and collect temporary or replacement devices.

The user interface is designed to guide users through the process without requiring extensive training or documentation.

1.1 Change history

Version	Description
IMP1753-14	Released with MyID 11.0.
IMP1753-15	Released with MyID 11.1.
IMP1753-16	Released with MyID 11.2.
IMP1753-17	Released with MyID 11.3.
IMP1753-18	Released with MyID 11.4. New <code>TermsAndConditionsTimeoutSeconds</code> option.
IMP1753-19	Released with MyID 11.5.
IMP1753-20	Released with MyID 11.6.

2 Installing the Self-Service Kiosk

2.1 Prerequisites

The Self-Service Kiosk requires the following software:

- .NET Framework 4.8
You must have .NET 4.8 installed on your client PCs. MyID is developed and tested using .NET Framework 4.8; if you need to use a later version of the .NET Framework, contact customer support quoting reference SUP-283.
- Windows Installer 4.5 or above
The Self-Service Kiosk installation program requires Windows Installer.
- MyID BioPack
If you intend to use biometric readers on the client PCs, you must install BioPack package of biometric components on each client PC on which you want to use biometrics. Run the BioPack client installation program that is installed to the `Utilities` folder on the MyID application server.

2.1.1 Communication between the Self-Service Kiosk and MyID

To allow your clients to communicate with the MyID server, your PC must be able to communicate with the URLs of the MyID web services; for example:

```
https://myserver/MyIDProcessDriver/
```

```
https://myserver/MyIDDDataSource/
```

Where `myserver` is the name of the server on which the MyID web services are installed.

You are recommended to set up SSL on the connection between the Self-Service Kiosk clients and the MyID web services. See section 4.4, [Setting up SSL](#) for details.

2.1.2 Minimum client PC specifications

Your client PC must meet the following minimum specifications:

- 1 GHz 32-bit (x86) or 64-bit (x64) processor
- 1 GB RAM (32-bit) or 2 GB RAM (64-bit)
- 2 GB hard disk free space
- The Self-Service Kiosk supports the following resolutions:
 - ◆ 1024x768
 - ◆ 1280x1024
 - ◆ 1920x1080
- Network access

2.1.3 Supported operating systems

The Self-Service Kiosk is supported on the following client operating systems:

- Windows 7 (32-bit)
- Windows 7 (64-bit)
- Windows 8.1 (32-bit)

- Windows 8.1 (64-bit)
- Windows 10 (32-bit)
- Windows 10 (64-bit)

2.1.4 Supported biometrics

The Self-Service Kiosk supports the following devices for biometric verification:

- Cross Match Verifier 300 (Windows 7 32-bit only)
- Cross Match Verifier 310 (Windows 7 32-bit and 64-bit only)
- SecuGen Hamster IV
- SecuGen iD-USB-SC/PIV
- SecuGen Hamster Pro Duo SC/PIV
- U.are.U 5300

Biometric verification is supported only on MyID PIV systems. It is not supported on MyID Enterprise systems.

2.2 Running the installation program

The installation program for the Self-Service Kiosk is provided in the following location within the MyID release:

```
MyID Clients\Self Service Kiosk\
```

Note: You do not need to have administrative privileges to install the Self-Service Kiosk. However, you must make sure that you have the correct permissions to install software to the program folder; for example, your system administrator may not permit you to install software to the default `Program Files (x86)\Intercede\` folder. In this case, choose a different destination location during the installation process.

To install the Self-Service Kiosk on your client PC:

1. Copy the installation program to a local drive.
If you do not run the installation program from a local drive, you may experience problems with the Kiosk running slowly due to certificate checks.
2. Run the `.msi` installer.
3. Click **Next**.
4. Select the destination location.

By default, the Self-Service Kiosk installs to:

```
C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk\
```

On a 32-bit system, this is:

```
C:\Program Files\Intercede\MyIDSelfServiceKiosk\
```

5. Click **Next**.
6. In the **Server URL** box, type the location of the server on which the MyID Web Services are installed.

For example:

```
https://myserver/
```

Note: Make sure you use the correct protocol: `http` or `https`.

7. In the **SSL Certificate Issuer DN** box, type the Issuer DN of the client-side certificate used to authenticate the client to the server for two-way SSL.

This is optional.

8. Click **Next**.
9. Click **Install**.
10. When the installer has completed, click **Finish**.

Note: The shortcut to the Self-Service Kiosk is created only for the current user.

2.2.1 Installing the Self-Service Kiosk silently

To install silently on a client PC, you can use the `.msi` installer with the following command-line parameters:

```
msiexec /i "<msi path>" /lv <LogFile> /q SSA_SERVERNAME=<ServerURL>  
SSLCERTIFICATEDN=<sslcertdn> INSTALLDIR=<InstallationFolder>
```

where:

- `<msi path>` is the path to the `.msi` file.
- `<LogFile>` is the name of the file to which you want to write a verbose log. This is optional.
- `<server url>` is the URL of the server on which the MyID Web Services are installed.
Note: Make sure you use the correct protocol: `http` or `https`. Also, you must include the trailing slash (`/`).
- `<sslcertdn>` is the Issuer DN of the client certificate used to authenticate the client to the server for two-way SSL. This is optional.
- `<InstallationFolder>` is the name of the folder to which you want to install the application. This is optional.


Note: Do not put a space character on either side of the `=` sign in the command line.

For example:

```
msiexec /i "C:\install\<installer>.msi" /lv msilog.txt /q  
SSA_SERVERNAME=https://myserver/ INSTALLDIR="C:\temp\ssk"
```

3 Overview

3.1 Architecture




The Self-Service Kiosk passes requests through HTTP or HTTPS to the MyID Data Source and MyID Process Driver web services; both services are required for full operation. The web services communicate using DCOM with the MyID components on the application server; these components provide the business logic and communicate with the MyID database. Responses are returned to the client through the MyID web services.

The web services, components and database may be on separate servers, or on the same server. The two web services must be installed on the same server.

The range of operations you can perform with the Self-Service Kiosk depends on the edition of MyID you are using – you can perform different operations with the PIV and Enterprise editions.

3.2 Self-Service Kiosk

The Self-Service Kiosk is designed to run in a public space with users having little or no MyID experience. The Self-Service Kiosk guides users through self-service operations such as card activation. Ideally, the Self-Service Kiosk should run on a dedicated shared PC, and run at startup.



A simple scenario would be:

1. A cardholder who has been issued a card that needs to be activated approaches the Kiosk and inserts their card.
2. The Kiosk detects that an Activation job is available for the device.
3. The Kiosk guides the user through the process of activating their card.

3.3 Authentication

The cardholder can authenticate to the MyID server using the following methods:

Method	Self-Service Kiosk
Smart card logon	Y
Security phrase logon	Y
Windows authentication	N
Authentication codes	Y
Logon codes	Y
Biometric logon	For unlocking only

See the MyID documentation for details of setting up the various types of authentication. The Self-Service Kiosk uses the same configuration for authentication as MyID Desktop clients.

When you set up the roles for access to particular workflows, you must make sure that the role has the correct logon methods; for example, if you add all the workflows to the Applicant role, and are using security phrase logon, you must set the Applicant role to have access to the Password logon mechanism.



3.4 Self-Service Kiosk features

Control over which features are available to Self-Service Kiosk users is maintained within MyID by using the standard roles mechanism.

Cardholders who use the Self-Service Kiosk must have permission to log on to MyID using passwords; for example, by having a role that has access to these workflows and that has **Password** selected in its **Logon Methods**. For example, if you grant the cardholders the Applicant role, then add all the workflows to the Applicant role, you must set the Applicant role to have access to the Password logon mechanism.

Use the **Edit Roles** workflow to specify which workflows are available.

The Self-Service Kiosk can carry out the following operations:

- Check for outstanding jobs for the current user.
- Collect a card.
Requires access to the **Collect My Card** workflow.
- Activate a card.
Requires access to the **Activate Card** workflow.
Note: This is not supported on MyID Enterprise.
- Update a card.
Requires access to the **Collect My Updates** workflow.
- Request and collect a replacement card.
Requires access to the **Collect My Card** and **Replace My Card** workflows.
- Collect a certificate renewal.
Requires access to the **Collect My Certificates** workflow.
- Issue a temporary card
Requires access to the **Request My Temporary Card** workflow.
- Reset the PIN and unlock the card
Requires access to the **Unlock Card** and **Unlock My Card** workflows.

4 Configuring the Self-Service Kiosk

4.1 Setting errors to silent

If you insert an unrecognized card, the Self-Service Kiosk may present an error dialog *behind* the Kiosk window. On an unattended Kiosk, there may be no way to close the error dialog. As a workaround, you can set a value in the registry to prevent the error dialog appearing.

1. On the Self-Service Kiosk PC, browse to the `Card Drivers` key.

On a 64-bit system, this is:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\Intercede\Edefice\Card Drivers\
```

On a 32-bit system, this is:

```
HKEY_LOCAL_MACHINE\SOFTWARE\Intercede\Edefice\Card Drivers\
```

2. If the `Card Drivers` key does not exist, create it.
3. Create a DWORD value called `silent`, and set the value to 1.

Note: This configuration affects all MyID clients on the same PC – Self-Service Kiosk, Self-Service App, and MyID Desktop.

4.2 Server location

The Self-Service kiosk is configured to communicate with the MyID Web Services server when you install the Self-Service Kiosk. If you want to change the server, you can edit the configuration file.

To edit the configuration file:

1. On the client PC, back up the `MyIDKiosk.exe.config` file in the following folder:

```
C:\Program Files\Intercede\MyIDSelfServiceKiosk\
```

On 64-bit systems, this is:

```
C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk\
```

2. Using a text editor, open the `MyIDKiosk.exe.config` file.

Note: Make the changes to the config file exactly as shown. The case is important.

3. Edit the `value` parameter in the following line:

```
<add key="Server" value="http://myserver.example.com/"></add>
```

For example:

```
<add key="Server" value="http://myserver2.example.com/"></add>
```

4. Save the configuration file.
5. Restart the Kiosk.

4.3 Kiosk page timeout

The Self-Service kiosk is configured to time out after 30 seconds, and ends the current workflow after that period of inactivity. If you want to change the timeout, you can edit the configuration file.

To edit the configuration file:

1. On the client PC, back up the `MyIDKiosk.exe.config` file in the following folder:

```
C:\Program Files\Intercede\MyIDSelfServiceKiosk\
```

On 64-bit systems, this is:

```
C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk\
```

2. Using a text editor, open the `MyIDKiosk.exe.config` file.

Note: Make the changes to the config file exactly as shown. The case is important.

3. Add the following line to the `<appSettings>` section:

```
<add key="PageTimeoutSeconds" value="30"></add>
```

The value is the timeout in seconds; in this example, 30 seconds.

4. If you want to specify a separate timeout for the Terms and Conditions screen, add the following line to the `<appSettings>` section:

```
<add key="TermsAndConditionsTimeoutSeconds" value="60"></add>
```

The value is the timeout in seconds; in this example, 60 seconds. If you do not set this option, the `PageTimeoutSeconds` value is used; if neither is specified, the default of 30 seconds is used.

5. Save the configuration file.
6. Restart the Kiosk.

4.4 Setting up SSL

4.4.1 One-way SSL

If you want to configure the Self-Service Kiosk to use one-way SSL for its communications with the MyID Web Services server, you must install the server's certificate under the Trusted Root Certification Authorities in the user's certificate store.

4.4.2 Two-way SSL

Note: If your server is set up to use two-way SSL, you must set up your client to use two-way SSL. If you do not use the `/ssl` command-line option, an error is displayed.

Note: The Self-Service Kiosk does not support two-way SSL using a certificate stored on a smart card.

To use two-way SSL using a specific certificate:

1. Install the client certificate in the user's personal store.

The client certificate must have the Client Authentication application policy – this has the following OID:

```
1.3.6.1.5.5.7.3.2
```

Note: Make sure that you issue the client certificate from a different certificate authority from the one you use to issue certificates to end users.

2. Find the client certificate's serial number:
 - a) Run the `CertMgr.msc` snap-in.
 - b) Expand **Personal > Certificates**.
 - c) Double-click the client certificate.
 - d) Click the **Details** tab.
3. Run the application using the following command line:

```
MyIDKiosk.exe /ssl /sslsn:<serial number>
```

where:

<serialnumber> – the serial number of the client certificate. Enter the serial number without spaces. For example, if the serial number is:

```
62 00 00 00 34 fe 3c a9 a8 1c 98 6a f1 00 00 00 00 00 34
```

use the following command line

```
MyIDKiosk.exe /ssl /sslsn:6200000034fe3ca9a81c986af1000000000034
```

Note: If you copy the serial number from the **Details** tab of the certificate properties dialog, you may inadvertently copy a non-printing character at the start of the serial number. You must make sure that you delete this character from the Kiosk command line. (Position the cursor before the `:` in the command line. Press the right-cursor key once. The cursor appears after the colon. Press the right-cursor key again. If the cursor does not move to after the first number in the serial number, there is a non-printing character present; press the Backspace key to delete it.)

If you run the application with the `/ssl` command line option but omit the `/sslsn` option, the application carries out the following:

1. The application checks the application settings file for the details of the last certificate that was successfully used to log on.
2. If no details are found, if the certificate is no longer in the personal store, or the server rejects the certificate, the application searches the personal store for certificates that match the issuer DN (optionally set up when you install the application) and have the Client Authentication policy.
3. If more than one certificate is found, the application displays a list of certificates for the user to select.

When the application has successfully logged on to the server using a certificate, the certificate's details are stored in the user's application settings file.

4.5 Accessing the web services for the first time

If you access the Kiosk after the web services have been installed on the server, you may experience a timeout that prevents the Kiosk from operating. This is caused by the processing required by the web services when they are first accessed.

As a workaround, you can access the web service page using a web browser before attempting to use the Kiosk. Access the following web page:

```
http://myserver/myidprocessdriver/processdriver.aspx
```

where `myserver` is the name of the web services server.

4.6 Running the Self-Service Kiosk

The installation program creates a shortcut for the Self-Service Kiosk. You are recommended to run the application in one of the following ways:

- Run the Self-Service Kiosk using the shortcut icon.
- Run the Self-Service Kiosk using a Windows Logon script, or by putting a shortcut in the Startup program group.

This starts up the Kiosk when the user logs in to Windows, and is appropriate for a stand-alone shared PC used exclusively as a kiosk.

4.6.1 Command-line parameters

To run the Self-Service Kiosk from the command line:

1. Open a command prompt and change to the Kiosk folder:

```
C:\Program Files\Intercede\MyIDSelfServiceKiosk\
```

On a 64-bit system, this is:

```
C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk\
```

2. Type the following, and press Enter:

```
MyIDKiosk.exe
```

To run the Kiosk in Derived Credentials mode, use the following command line:

```
MyIDKiosk.exe /dc
```

4.6.2 Closing down the Kiosk

The Kiosk does not have an on-screen control to allow you to shut it down, as it is meant to run continuously. When an administrator needs to shut the Kiosk down, you can do so as follows:

- On the keyboard, press ALT+F4.

4.7 Translating the user interface

The Self-Service Kiosk supports translation of the on-screen text to change the terminology used or to change the language completely.

For example, the on-screen contact details are held in the dictionary with the ID 9100403.

Contact Intercede customer support for details, quoting reference SUP-71.

4.8 Logging

You can set up your Self-Service Kiosk to write debug information to a log file. You may need to provide this information to Intercede customer support.

Contact customer support quoting reference SUP-236.

4.9 Job filtering

You may not want every client application to handle every job that is available for the cardholder. For example, you may want your Self-Service Kiosks to handle only activation jobs, and require your cardholders to use their Self-Service Apps to handle all other jobs on their own workstations. You can set up the web service to provide a customized list of jobs.

See the [Web Service Architecture Installation and Configuration Guide](#) for details of setting up job filtering; this document is provided with the software update that installs the web services.

4.10 Temporary credential profile

The Issue Temporary Card option in the Self-Service Kiosk issues a temporary card to the user. If you set the **Temporary Credential Profile Name** configuration option, the Kiosk issues a temporary card using the specified credential profile. If you do not set this option, the credential profile used for the original card is used.

See the [Administration Guide](#) for details of setting up a credential profile for temporary replacement cards.

To set the temporary credential profile:

1. From the **Configuration** category, select **Operation Settings**.
2. On the **General** tab, set the following option:
 - **Temporary Credential Profile Name** – set this to the name of a credential profile to be used for temporary cards.
3. Click **Save changes**.

The card profile must be available to all cardholders you want to be able to obtain temporary cards through the Self-Service Kiosk. If this profile requires validation, the Issue Temporary Card option in the Kiosk will allow the cardholder only to request a temporary card, not collect it; if the profile does not require validation, a cardholder can use the Issue Temporary Card option in the Kiosk to request and collect a temporary card.

4.11 Signature validation

The Self-Service Kiosk performs signature validation at startup to ensure that all components are properly signed by Intercede and have not been tampered with. These checks are performed using the native Windows APIs, and may require the client to connect to the Internet to retrieve the latest Certificate Revocation Lists (CRLs) for revocation checks of the Intercede signing certificate. If the client is permanently running in an isolated environment without access to the Internet, the CRLs cannot be retrieved, which can cause signature verification to fail. Under these circumstances, you may see an error similar to the following:

```
Failed to verify signature for running application. Error Code: 128
```

This error usually indicates that the client is unable to perform its revocation checks; to continue, you must disable these checks by adding an option to the application configuration file.

To edit the configuration file:

1. On the client PC, shut down the Self-Service Kiosk.
2. Back up the `MyIDApp.exe.config` file. By default, this is in the following folder:
`C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk\`
3. Using a text editor, open the `MyIDKiosk.exe.config` file.

Note: Make the changes to the config file exactly as shown. The case is important.

4. Edit the `value` parameter in the following line:

```
<add key="ComponentVerificationSkipRevocationChecks"  
value="TRUE"></add>
```

If this line does not exist, you can add it to the `<appSettings>` section.

5. Save the configuration file.

6. Restart the Self Service Kiosk.

When this option is enabled, the client performs all of its normal validation, but does not perform the revocation check. As the client does not need to retrieve the CRLs, it does not need to be connected to the Internet.

Note: This reduces the integrity of the signature validation, as the client will be unable to determine if any of the certificates in the chain have been revoked since signing occurred – as such, you should ensure that the client's configuration file is modifiable only by users with administrative privileges.

5 Troubleshooting

- **Inserting an unknown card type causes the Kiosk to fail**

If you insert an unknown card type, and the Kiosk appears to stop working, it is possible that an error window has opened behind the Kiosk window. See the *Error when unrecognized card is inserted* entry in section 6, *Known Issues*.

- **You do not have sufficient privileges to perform this operation**

When inserting either a known or unknown card, you may see an error similar to:

```
You do not have sufficient privileges to perform this operation
```

This is because you do not have access to the workflow. Make sure that the **Server Credentials** role has access to the **Request Derived Credential** workflow.

6 Known Issues

- **CrossMatch Verifier outer edges issue**

A problem currently exists where the outer edges of the finger print reader do not detect the finger when placed on the scanner plate of a CrossMatch Verifier. A finger placed in the centre of the scanner plate is detected correctly.

- **CrossMatch Verifier first time operations**

When you scan a fingerprint for the first time using a CrossMatch Verifier, the scan does not work: the capture area lights up but no fingerprint is received by the Self-Service Kiosk. However, if you restart the Self-Service Kiosk and rescan it operates correctly.

- **Cannot run the Self-Service Kiosk if MyID is open in a browser**

You cannot run the Self-Service Kiosk if you have an Internet Explorer window open at the MyID webpage. This is because both the Self-Service Kiosk and the MyID web application conflict with each other over card transaction locking.

- **Cannot choose a card in the Self-Service Kiosk**

If you have more than one card reader, the Self-Service Kiosk does not allow you to select which reader to use. If you have unissued smart cards in more than one reader, and are collecting a card issuance job, the Self-Service Kiosk will select one of the cards without any user intervention.

- **Self-Service Kiosk and Virtual Smart Cards**

The Self-Service Kiosk does not currently support Virtual Smart Cards. If you want to use Virtual Smart Cards with the Kiosk, contact customer support for more information.

- **Compatibility with previous versions of the biometric components**

There is no backwards compatibility with older version of the MyID biometric components (BioPack). A future release will provide backwards compatibility.

- **Timeout after installation**

If you access the Kiosk after the web services have been installed on the server, you may experience a timeout that prevents the Kiosk from operating. This is caused by the processing required by the web services when they are first accessed.

As a workaround, you can access the web service page using a web browser before attempting to use the Kiosk. Access the following web page:

```
http://myserver/myidprocessdriver/processdriver.aspx
```

where `myserver` is the name of the web services server.

- **Error entering multiple lines of text for replacement card reasons**

When requesting a replacement card using the Self-Service Kiosk, you are prompted to enter a reason for the replacement. If you enter multiple lines of text, an error is displayed. As a workaround, enter a single line of text.

- **Truncated text at low screen resolutions in Self-Service Kiosk**

If you run the Self-Service Kiosk at a screen resolution of 1024x768, some text may be truncated. As a workaround, run the Self-Service Kiosk at a resolution of 1280x1024 or 1920x1080.

- **Error when installing**

You may see an error similar to the following when installing the Kiosk:

```
Error 1301. The installer has insufficient privileges to access this
directory:
C:\Program Files (x86)\Intercede\MyIDSelfServiceKiosk.
The installation cannot continue. Log on as an administrator or
contact your system administrator.
```

You do not need to have administrative privileges to install the Self-Service Kiosk. However, you must make sure that you have the correct permissions to install software to the folder you have selected; for example, your system administrator may not permit you to install software to the default folder. In this case, choose a different destination location during the installation process.

- **Problems collecting or updating cards**

If you experience problems when collecting or updating cards, try increasing the **Certificate Refresh Threshold** option on the **Certificates** tab of the **Operation Settings** workflow to a higher value; for example, 45.

This problem may manifest with an error similar to:

```
One of the certificates that have been requested for you has failed
to issue. Please contact your administrator.
```

Note that the certificate may have issued correctly even though the card update has failed.

- **Enter PIN twice for card update and certificate renewal jobs**

If you have terms and conditions enabled for the credential profile, and the **Terms and Conditions During Device Update** configuration option is set to *Yes*, you are required to enter the PIN both before the terms and conditions are displayed and after accepting the terms and conditions.

- **Cannot process any jobs until a VSC job has been collected**

If a user has more than one job to be collected, and one of them is a Virtual Smart Card (VSC) job, you must collect the VSC (for example, using the Self-Service App) before you can process any of the other jobs.